ode45 - Differential Equation Solver

This routine uses a variable step Runge-Kutta Method to solve differential equations numerically. The syntax for **ode45** for first order differential equations and that for second order differential equations are basically the same. However, the .m files are quite different.

I. First Order Equations
$$\begin{cases} y' = f(t, y) \\ y(t_0) = y_0 \end{cases}$$

- A. Create a .m file for f(t, y) (see the tutorial on numerical methods and m files on how to do this). Save file as, for example, **yp.m**.
- B. Basic syntax for $\mathbf{0de45}$. At a MATLAB prompt type :

[t,y]=ode45('yp',[t0,tf],y0); (your version of ode45 may not require brackets around t0, tf)

yp = the .m file of the function f(t,y) saved as yp.m t0, tf = initial and terminal values of t y0 = initial value of y at t_0

C. For example, to numerically solve $\begin{cases} t^2y' = y + 3t \\ y(1) = -2 \end{cases}$ over the interval $1 \le t \le 4$:

• Create and save the file yp.m for the function $\frac{1}{t^2}(y+3t)$.

• At a MATLAB prompt type:

[t,y]=ode45('yp', [1,4],-2); (your version of ode45 may not require backets around [1,4])

- To print results type : [t,y]
- To plot results type : plot(t,y)
- To plot results type with a '+' symbol : plot(t,y,'+')

II. Second Order Equations
$$\begin{cases} y'' + p(t) y' + q(t) y = g(t) \\ y(t_0) = y_0 \\ y'(t_0) = y_1 \end{cases}$$

A. First convert 2^{nd} order equation above to an equivalent system of 1^{st} order equations. Let $x_1 = y, x_2 = y'$:

$$\begin{cases} x_1' = x_2 \\ x_2' = -q(t) x_1 - p(t) x_2 + g(t) \end{cases}, \text{ where } x_1(t_0) = y_0, \ x_2(t_0) = y_1. \end{cases}$$

B. Create and save a .m file which will return a <u>vector-valued</u> function. This is a little tricky so here is a specific example. Suppose the system is as below and $0 \le t \le 4$

$$\begin{cases} x_1' = x_2 \\ x_2' = -t x_1 + e^t x_2 + 3\sin 2t \end{cases}, \text{ where } x_1(0) = 2, \ x_2(0) = 8.$$

• Create the following function file and save it as F.m :

```
function xp=F(t,x)
xp=zeros(2,1); % since output must be a column vector
xp(1)=x(2);
xp(2)=-t*x(1)+exp(t)*x(2)+3*sin(2*t); % don't forget ; after each line
```

 $\bullet\,$ Basic syntax for $\,$ ode45 . At MATLAB prompt, type :

```
[t,x] = ode45('F', [t0,tf], [x10,x20]);
\begin{cases}
F = the .m file of the vector-function saved as above t0, tf = initial and terminal values of t x10 = initial value of x1 at t0 : x10 = x1(t_0) x20 = initial value of x2 at t0 : x20 = x2(t_0)
\end{cases}
```

The example above becomes : [t,x] = 0de45('F', [0,4], [2,8]);

• Since $x_1(t) = y$, to print out the values of the solution y for $t_0 \le t \le t_f$, type :

[t,x(:,1)]

To plot the solution on a graph t vs y, type : plot(t,x(:,1))

(This is because the vector **x** has 1^{st} component $x_1 = y$ and 2^{nd} component $x_2 = y'$.)

• To plot x_1 vs x_2 (phase plane) type : plot(x(:,1),x(:,2))